

_TMSTARTSERVER(3)

| |
|-------------------------|
| REVISION HISTORY |
|-------------------------|

| NUMBER | DATE | DESCRIPTION | NAME |
|--------|------|-------------|------|
| | | | |

Contents

| | | |
|----------|---------------------|----------|
| 1 | SYNOPSIS | 1 |
| 2 | DESCRIPTION | 2 |
| 3 | RETURN VALUE | 3 |
| 4 | ERRORS | 4 |
| 5 | BUGS | 5 |
| 6 | EXAMPLE | 6 |
| 7 | SEE ALSO | 7 |
| 8 | COPYING | 8 |

Chapter 1

SYNOPSIS

```
#include <atmi.h>
```

```
int _tmstartserver( int argc, char **argv, struct tmsvrargs_t tmsvrargs);
```

Link with *-latmisrvnomain -latmi -lubf -lnstd -lpthread -lrt -lm*

Chapter 2

DESCRIPTION

Function is used to start Enduro/X XATMI server process. The startup routine takes standard command line arguments and additions structure *tmsvrargs* filled with **tpsvrinit(3)** and **tpsvrdone(3)** callbacks, it also contains the XA Switch object and array filled with services to be advertised after the user's **tpsvrinit(3)** is done. Any services which user have advertised by **tpadvertise(3)** and which have also exported to *tmsvrargs.svctab*, will be ignored (i.e. **TPEMATCH** error will be ignored). The *tmsvrargs.svctab* table must be terminated with row for which *svcnm* is set to NULL.

The **struct tmsvrargs_t** structure is following:

```
struct tmsvrargs_t
{
    struct xa_switch_t * sw;           /**< XA Switch */
    struct tmdsptchtbl_t *svctab;     /**< Service dispatch table */
    long rful;                         /**< Reserved for future use */
    int (*p_tpsvrinit)(int, char **); /**< Server init function */
    void (*p_tpsvrdone)(void);        /**< callback to server done */
    void * rfu2;                       /**< Reserved for future use */
    void * rfu3;                       /**< Reserved for future use */
    void * rfu4;                       /**< Reserved for future use */
    void * rfu5;                       /**< Reserved for future use */
    void * rfu6;                       /**< Reserved for future use */
};
```

The **struct tmsvrargs_t** structure is following:

```
struct tmdsptchtbl_t
{
    char *svcnm;                       /**< Service name */
    char *funcnm;                      /**< Function name */
    void (*p_func)(TPSVCINFO *);       /**< Function to run on service invocation*/
    long rfu1;                         /**< Reserved 1 */
    long rfu2;                         /**< Reserved 2 */
};
```

RFU bits should be initialized to 0 or NULL.

Chapter 3

RETURN VALUE

On success, `_tmstartserver()` returns 0; on error, -1 is returned, with `tperrno` set to indicate the error.

Chapter 4

ERRORS

For error records see NDRX and/or ULOG records.

Chapter 5

BUGS

Report bugs to support@mavimax.com

Chapter 6

EXAMPLE

See `atmitest/test004_basicevent/atmisv4_1ST.c` for sample code.

Chapter 7

SEE ALSO

`ndrx_main(3)` `ndrx_main_integra(3)`

Chapter 8

COPYING

© Mavimax, Ltd
