

XADMIN(8)

REVISION HISTORY			
NUMBER	DATE	DESCRIPTION	NAME

Contents

1	SYNOPSIS	1
2	DESCRIPTION	2
3	COMMANDS	3
4	CONFIGURATION	9
5	SAMPLE CONFIGURATION	10
6	EXIT STATUS	11
7	BUGS	12
8	SEE ALSO	13
9	COPYING	14

Chapter 1

SYNOPSIS

xadmin [*COMMAND*] [*OPTIONS*]

Chapter 2

DESCRIPTION

xadmin is command line interface to Enduro/X. It is administration utility. Which is servers as communication interface between Enduro/X ATMI local daemon and administrator. *xadmin* can receive commands as parameter to *xadmin*. It can read command from pipe (stdin). And it can work in interactive mode. In this case *xadmin* is started with no parameters.

xadmin is responsible to start idle instance of *ndrxd*. After that *xadmin* sends commands to *ndrxd* and prints the response from daemon to the stdout in human readable form. Commands are sent and response from *ndrxd* are received via POSIX Queues.

xadmin can lookup the configuration (currently used for user specific generators). The configuration search order is following:

1. INI file by *NDRX_XADMIN_CONFIG* environment variable. This can also be a directory. The common-config routines will load all configs (.ini .cfg, .conf, .config) files.
2. INI file in *\$HOME/.xadmin.config*;
3. INI file in */etc/xadmin.config*;

Chapter 3

COMMANDS

quit

Quit from command line utility

q

Alias for quit

exit

Alias for quit

echo

Echo text back to terminal

idle

Enter daemon process in idle state (if not started)

help

Print help (this output)

stat

Prints general status information

poller

Print polling sub-system name i.e. **epoll** - when build is using Linux e-poll sub-system, this allows true one queue multiple server approach to be used. **kqueue** - the same benefits as for Linux **epoll** only on BSD platform, **SystemV** - for this build System V queues are used (instead for others Posix queues are used). In case of System V still one queue multiple servers are available with configuration of request address. **poll** - this is worst mode for Enduro/X as only Round Robin message distribution is available for dispatching messages to servers. This uses only standard features of Posix queues. The poller is built in the distribution and cannot be changed via configuration, only possible changing is with reinstalling other Enduro/X build.

ldcf

Load configuration

start [-y] [-s <server>] [-i <srvid>]

Start application domain. If config not loaded, it loads configuration automatically. **-y** means do not ask for confirmation. **-s** means ATMI servers binary name to be started, instead of whole application domain. **-i** means start specific server instance. In case if **ndrxd(8)** was busy with other session tasks (other terminal start/stop or internal server reload on limited memory use), the xadmin will re-attempt to send message to **ndrxd** before giving up. The number of attempts are configured in **NDRX_NORMWAITMAX** environment variable (default is 60), between attempts 1 second sleep is done. see **ex_env(5)**.

psc

Print services

stop [-y] [-s <server>] [-i <srvid>] [-k] [-f]

Stop application domain. *-y* means do not ask for confirmation. *-s* means ATMI servers binary name to be stopped, instead of whole application domain. *-i* means stop specific server instance. *-k* flag will keep *ndrxd* running, and protected servers will not be shutdown. In case if **ndrxd(8)** process is doing start or stop for other xadmin session (or doing internal server reloads in case if memory limits reached), then command will perform several re-attempts for executing the command. The attempts are configured in **NDRX_NORMWAITMAX** environment variable. Between attempts, 1 second sleep is done. In case if **stop** command was unable to send message to **ndrxd**, command will exit with failure, and will not wait for **ndrxd** termination. In case if *-f* force flag is set, the xadmin will wait indefinitely until **ndrxd** will not be found in the system. No matter message was sent to ndrxd or not. see **ex_env(5)**.

sreload [-y] [-s <server>] [-i <srvid>]

Reload application domain - restart server instance by instance. Configuration be loaded prior. *-y* means do not ask for confirmation. *-s* means ATMI servers binary name to be reloaded, instead of whole application domain. *-i* means restart specific server instance.

sr

Alias for *sreload*

psc

Print available services.

down [-y]

Force appserver shutdown & resources cleanup. RUN ONLY IF YOU KNOW WHAT YOU ARE DOING! Basically this kills all ATMI servers and Enduro/X daemon. This does NOT remove client processes.

cat

Attached console to ndrxd user session in progress

reload

Load new configuration

testcfg

Test new configuration

unadv -i server_id -s service_name

Un-advertise service. *-i* is server id, *-s* is service name to be unadvertised.

readv -i server_id -s service_name

Re-advertise service. Might be usable if service Q was unlinked. *-i* is server id, *-s* is service name to be re-advertised.

restart [-y] [-s <server>] [-i <srvid>]

Restart app or service (invokes start & stop with same args!). *-y* makes to not to ask for confirmation. *-s* is server/binary name. *-i* is server ID.

r

Alias for *restart*

-v

Print version info

ver

Alias for *-v*

ppm [-2]

Print process model. The argument *-2* show second page of process model attributes.

psvc

Shared mem, print services

psrv

Shared mem, print servers

cabort [-y]

Abort shutdown or startup operation in progress. -y do not ask for confirmation.

sreload [-y] [-s <server>] [-i <srvid>]

Restart servers instance by instance

pq

Print Queue statistics from ndrxd.

pqa [-a]

Print all queues including client and admin Q. -a includes other prefix queues.

pt

Print global transactions in progress.

printtrans

Alias for *pt*.

abort -t <transaction_manager_reference> -x <XID> [-g <resource_manager_id>] [-y]

Abort transaction. -g does abort single resource manager's transaction. -y is for auto confirmation.

aborttrans

Alias for *abort*.

commit -t <transaction_manager_reference> -x <XID> [-y]

Commit transaction. -y is for auto confirmation.

committrans

Alias for *commit*.

recoverlocal [-s <TM SERVICE>]

List local/for each TMSRV heuristic in-doubt transactions. This makes query to RM with xa_recover. With -s flag specific TMSRV service can be specified. otherwise all visible TMSRV servers are queried.

commitlocal [-s <TM SERVICE> [-x <XID>]] [-y]

Commit in-doubt transaction. If -x xid reported by recoverlocal is not specified, then all transactions are tried to be committed. If -s is set then specific TMSRV instance service is queried. If -x is set, -s must be set too, because specific XID must be part of some specific instance. The status of particular operation is reported back to stdout. Note that only prepared transactions can be processed by this command. Heuristically committed/aborted transaction may be only forgot. If so, context errors may be given.

abortlocal [-s <TM SERVICE> [-x <XID>]] [-y]

Abort in-doubt transaction. If -x xid reported by recoverlocal is not specified, then all transactions are tried to be aborted. If -s is set then specific TMSRV instance service is queried. If -x is set, -s must be set too, because specific XID must be part of some specific instance. The status of particular operation is reported back to stdout. Note that only prepared transactions can be processed by this command. Heuristically committed/aborted transaction may be only forgot. If so, context errors may be given.

forgetlocal [-s <TM SERVICE> [-x <XID>]] [-y]

Abort in-doubt transaction. If -x xid reported by recoverlocal is not specified, then all transactions are tried to be forgotten. If -s is set then specific TMSRV instance service is queried. If -x is set, -s must be set too, because specific XID must be part of some specific instance. The status of particular operation is reported back to stdout.

pe

Print Environment variables of *ndrxd* process.

printenv

Alias for *pe*.

set ENV_NAME=ENV VALUE

Set environment value. The value of env variable is parsed as command line arguments. Prior sending to *ndrxd* they are concatenated with spaces in between.

unset ENV_NAME

Unset environment variable

pc

Print client processes. This sends command to Client Process Monitor server (*cpmsrv*).

bc -t <process_tag> [-s <sub_section>] [-w <wait_time>]

Boot client process. This sends command to Client Process Monitor server (*cpmsrv*). Processes are registered in *ndrx-config.xml* *<clients>* section. If sub section is not specified, then default value is minus sign (-). The *process_tag* and *sub_section* can contain wildcards percent (%) sign. Then boot process will be executed in batch mode and progress will be returned to the xadmin's output. When running in batch mode *wait_time* is time in milliseconds to sleep after each matched process is marked for start. Note that *wait_time* shall be less than global timeout specified in *NDRX_TOUT* env variable (or *cconfig* [*@global*] section).

sc -t <process_tag> [-s <sub_section>] [-w <wait time in milliseconds>]

Stop client process. This sends command to Client Process Monitor server (*cpmsrv*). The process is stopped by *process_tag* and optional *sub_section*. If sub section is not specified, then default value is minus sign (-). The *process_tag* and *sub_section* can contain wild-card percent sign (%), then stopping is executed in batch mode (stop all matched running processes). If *wait_time* is specified then in batch mode it is sleep in milliseconds after each stopped process. Note that *wait_time* shall be less than global timeout specified in *NDRX_TOUT* env variable (or *cconfig* [*@global*] section). Also time needed for stopping shall be counted in. If the timeout occurs, *cpmsrv* will complete the operation anyway.

rc -t <process_tag> [-s <sub_section>] [-w <wait time in milliseconds>]

Reload client process. This sends command to Client Process Monitor server (*cpmsrv*). The process is reloaded (stopped/-marked for start) by *process_tag* and optional *sub_section*. If sub section is not specified, then default value is minus sign (-). The *process_tag* and *sub_section* can contain wild-card percent sign (%), then reloading is executed in batch mode (stop/start running processes one by one). If *wait_time* is specified then in batch mode it is sleep in milliseconds after each stopped process. Note that *wait_time* shall be less than global timeout specified in *NDRX_TOUT* env variable (or *cconfig* [*@global*] section). Also time needed for stopping shall be counted in. If the timeout occurs, *cpmsrv* will complete the operation anyway. The *wait_time* can be used in cases when reloading the binaries with out service interruption, in that case *wait_time* should contain the *cpmsrv*'s interval check time (*-i* flag) because for start operation binary is only marked for boot and not the booted. Basically this executes *sc/bc* for each of the matched processes.

mqlc

List queue configuration. This broadcasts the requests of config listing to all *tmqueue* servers. If flags column contains *D* flag, then it means that queue was dynamically defined and *QDEF* string contains values from default queue.

mqll

List actual queues allocated on system. Similarly as for *mqlc* this requests the information from all *tmqueue* servers. *#LOCK* column contains the number of active non committed messages in Q. *#SUCC* and *#FAIL* column contains number of processed messages for automatic queues (messages are sent to destination services automatically by *tmqueue* server).

mqrc

This command requests all queue servers to reload the configuration file.

mqllm -s <QSpace> -q <QName>

List messages in queue. *-s* is queue space name (set by *tmqueue -m* paramemter). The output lists the message ID in modified base64 version (/ changed to _).

mqldm -n <Cluster node id> -i <Server ID> -m <Message ID>

Dump/peek message to stdout. The values from *-n* (node id), *-i* (srvid), *-m* (message id) can be taken from *mqllm* command. This command prints to stdout, the *TQCTL* structure in form of UBF buffer and the message it self. If message is UBF, then UBF dump is made, otherwise hexdump of message is printed.

mqch -n <Cluster node id> -i <Server ID> -q <Q def (conf format)>

Change/add queue definition to particular *tmqueue* server. The format of the queue definition is the same as used *q.conf(5)* (see the man page). You may miss out some of the bits (except the queue name). Those other bits will be take from default q.

mqrm -n <Cluster node id> -i <Server ID> -m <Message ID>

Remove message from queue. You have to identify exact queue space server here by Enduro/X cluster id and server id.

mqmv -n <Source cluster node id> -i <Source server ID> -m <Source Message ID> -s <Dest qspace> -q <Dest qname>

Move the message from specific qspace server to destination qspace and qname. The bits from *TPQCTL* which are returned by *tpdequeue()* call are preserved in new *tpenqueue()* call. Note that for this call *xadmin* must be in invalid XA environment, so that distributed transaction can be performed.

killall <name1> [<name2> ... <nameN>]

Kill all processes given by *ps -ef*. The command does match the name in the line. If substring is found, then process is killed.

qrm <qname1> [<qname2> ... <qnameN>]

Remove specific Posix queue.

qrmall <substr1> [<substr2> ... <substrN>]

Remove queue matching the substring.

provision [-d] [-v<param1>=<value1>] ... [-v<paramN>=<valueN>]

Prepare initial Enduro/X instance environment, create folder structure, generate configuration files with ability to register all available services.

gen [-d] [-v<param1>=<value1>] ... [-v<paramN>=<valueN>]

Generate application sources. See the *xadmin*'s help for more details. Currently it is possible to generate C and Go sources and the UBF buffer headers for both languages. By running the command, wizards will be offered asking for different details. Which later can be reconfigured by **-d** - allowing to default the wizard, while **-v** allows to set wizard values from command line.

pubfdb

Print UBF custom fields database contents to the terminal.

cs <cache_db_name>|-d <cache_db_name>

Print cache contents (headers) to the terminal. The database name is specified in *cache_db_name* parameter.

cacheshow

Alias for *cs*.

cd -d <dbname> -k <key> [-i interpret_result]

Dump specified message to the terminal. With specified **-i** flag, the attempt for data interpretation will be made. For UBF buffers the output will be formatted with command **Bprint()**.

cachedump

Alias for *cd*.

ci -d <dbname> [-k <key>][-r use_regexp]

Invalidate cache. In case if only **-d** is specified, whole database will be dropped. Exact record may be dropped with **-k** flag. In case if **-r** is used, then key will be matched as regular expression over the data keys. In case if drop database is used, linked keygroup records are not processed. For other scenarios, linked records are processed according to the configuration.

cachedump

Alias for *cd*.

svmaps [-p] [-s] [-a] [-i] [-w]

Command is available only for System V messaging sub-system. Command prints the Queue ID (same ids from **ipcs** command) mappings to Posix queues used by Enduro/X. **-p** parameter (which is enabled by default) prints the mapping table from Posix Queue to System V. **-s** parameter uses reverse table by printing System V mappings to Posix. **-a** enables to print all the entries in the shared memory (there could be lots of lines printed. Totally set by **NDRX_MSGQUEUESMAX** environment variable). **-i** (used by default) prints only the queues which currently are in use. **-w** prints mappings which were in use, but currently are not in use. The **-i**, **-w** arguments can be combined.

shms

Shows currently open shared memory segments.

pmode

Prints technical information about Enduro/X build mode (basically *ndrx_config.h*).

ps [-a filter] [-b filter] [-c filter] [-d filter] [-r regexpfilter] [-p] [x pid]

Print running processes in system with command line arguments. This is similar to **ps -ef** in Linux or equivalents on other Operating Systems. Enduro/X **ps** command does not print the **xadmin** process, it is filtered out by default. The flags **-a**, **-b**, **-c** and **-d** are just a words that must be substring for the the ps output (i.e. basic grep). The **-r** argument is regular regular expression that must be matched. If none of these arguments are passed, then no filtering is done and max output is done (except the xadmin by it self). To enable printing PID only, use **-p** argument. To exclude particular PID from printing, use **-x** argument. The memory stats in kilobytes can be printed with turning on argument **-m** which must be used together with **-p**, then output is printed in format: "<pid>:<RSS>:<VSZ>", where RSS and VSS memory is printed in Kilobytes.

appconfig SETTING [NEWVALUE]

Change **ndrxconfig.xml(5)** "appconfig" section arguments dynamically for the process running. Settings available for changing are **sanity**, **checkpm**, **brrefresh**, **restart_min**, **restart_step**, **restart_max**, **restart_to_check**, **gather_pq_stats** and **rqaddrttl**. For their descriptions and possible values see **ndrxconfig.xml(5)** manpage. The syntax for command is that if **NEWVALUE** is not provided, then current value is printed. If **NEWVALUE** is provided, then value is changed and new value is printed to stdout. **ndrxd** must be running (or will be started in idle state). Note that configuration must be loaded in order to have non-error output from command.

dping [-c <loops>]

Perform ndrxd pings By default 4 loops are done, but this can be overridden by -c argument.

dsleep SLEEP_SEC

Put ndrxd in sleep mode, this is useful for debugging. Number of seconds to sleep are denoted in **SLEEP_SEC** argument.

mibget [-c <CLASS>] [-m]

This returns lists the **tm_mib(5)** objects in command line. The object classes are set in -c argument, where possible values are **T_CLIENT**, **T_DOMAIN**, **T_MACHINE**, **T_QUEUE**, **T_SERVER**, **T_SERVICE** and **T_SVCGRP**. The parameter **-m** returns the output in machine readable format.

udown [-y]

Remove all System V resources used by user. This includes any of: queues, shared memory and semaphores. -y is used for confirmation.

Chapter 4

CONFIGURATION

The following parameters from section [**@xadmin**] or [**@xadmin/(<\$NDRX_CCTAG>)**] are used (if config file is present):

gen scripts=*PATH_TO_GENERATOR_SCRIPTS*

This parameter configures the path where *xadmin* should look for .pscript files. The file names must be in following format: `gen_<lang>_<type>.pscript`. Basically <lang> and <type> will be offered as targets under \$xadmin gen command. The \$xadmin help will print these scripts. For script reference look in Enduro/X source code, **xadmin/scripts** folder. It is assumed that these scripts will inherit *WizardBase* class compiled into Enduro/X. This class is driving the wizard. Also note that each parameter which is asked to user enter into wizard, can be overridden from command line with **-v<param1>=<value1>**. The generator can be defaulted by **-d** argument.

Chapter 5

SAMPLE CONFIGURATION

For system wide settings the following file is created: **/etc/xadmin.config**:

```
[@xadmin]  
gen scripts=/development/templates
```

Chapter 6

EXIT STATUS

0 Success

1 Failure

Chapter 7

BUGS

Report bugs to support@mavimax.com

Chapter 8

SEE ALSO

`ndrxd(8)`, `q.conf(5)`, `tmqueue(8)` `cpmsrv(8)` `ex_env(5)`

Chapter 9

COPYING

© Mavimax, Ltd