

TX_OPEN(3)

REVISION HISTORY			
NUMBER	DATE	DESCRIPTION	NAME

Contents

1	SYNOPSIS	1
2	DESCRIPTION	2
3	RETURN VALUE	3
4	ERRORS	4
5	EXAMPLE	5
6	BUGS	6
7	SEE ALSO	7
8	COPYING	8

Chapter 1

SYNOPSIS

```
#include <tx.h>
```

```
int tx_open(void);
```

For XATMI client link with *-latmiclt -latmi -lubf -lnstd -lpthread -lrt -lm*

For XATMI server link with *-latmisrvl -latmisrvnomainl -latmisrvinteg -latmi -lubf -lnstd -lpthread -lrt -lm*

Chapter 2

DESCRIPTION

Connect to the XA resource manager. Note that environment for process must be configured, so that Enduro/X can load correct resource manager drivers. See the **ex_env(5)** man page for environment variables, that must be set. Basically Enduro/X will dynamically load library set in **NDRX_XA_DRIVERLIB** env variable. This is the driver which provides in unified way of getting **xa_switch**. As the xa_switches can be located in different Resource Managers, the second library might be need to load and that is marked in **NDRX_XA_RMLIB** env variable. The resource manager ID is set in **NDRX_XA_RES_ID** env variable. If your application needs different resource managers or different transaction branches, then you can use environment variable override functionality, see **ex_envover(5)** and **ndrxconfig.xml(5)**. XA connection strings for Enduro/X drivers are stored into **NDRX_XA_OPEN_STR** and **NDRX_XA_CLOSE_STR** variables. Enduro/X will try to init XA sub-system as soon as possible (i.e. load drivers, etc.). If to delay initial XA drivers loading till actual **tx_open(3)** call, then environment variable **NDRX_XA_LAZY_INIT** should be set to 1.

This function at lowest level, basically calls XA switches **xa_open_entry()** function with **NDRX_XA_OPEN_STR** string.

If **tx_open(3)** was already called and XA is initialized, then function will succeed, and no error will be generated.

TX API is base on TP API. This function is based on **tpclose(3)** and it is possible to mix these two API kinds.

Chapter 3

RETURN VALUE

On success, **tx_close()** return **TX_OK**; on error, error code is returned

Chapter 4

ERRORS

TX_FAIL Failed to open XA resource (cannot load Enduro/X XA driver, cannot load resource manager driver or resource manager returned

Chapter 5

EXAMPLE

See `atmitest/test021_xafull/atmict21tx.c` for sample code.

Chapter 6

BUGS

Report bugs to support@mavimax.com

Chapter 7

SEE ALSO

`tx_close(3)` `tpopen(3)` `tx_open(3)` `tx_commit(3)` `tx_rollback(3)` `tx_info(3)`

Chapter 8

COPYING

© Mavimax, Ltd