

TPCONVERT(3)

| REVISION HISTORY | | | |
|------------------|------|-------------|------|
| NUMBER | DATE | DESCRIPTION | NAME |
| | | | |

Contents

| | | |
|-------------------|------------------------------|-------------------|
| 1 | SYNOPSIS | 1 |
| 2 | DESCRIPTION | 2 |
| 3 | RETURN VALUE | 3 |
| 4 | ERRORS | 4 |
| 5 | EXAMPLE | 5 |
| 6 | BUGS | 6 |
| 7 | SEE ALSO | 7 |
| 8 | COPYING | 8 |

Chapter 1

SYNOPSIS

```
#include <atmi.h>
```

```
int tpconvert (char *str, char *bin, long flags);
```

For XATMI client link with *-latmiclt -latmi -lubf -lnstd -lpthread -lrt -lm*

For XATMI server link with *-latmisrvl -latmisrvnomainl -latmisrvinteg -latmi -lubf -lnstd -lpthread -lrt -lm*

Chapter 2

DESCRIPTION

Function is used to convert Enduro/X identifiers like client id, transaction id and XA two-phase commit xid to string representation. Function also offers to convert value from string back to binary (Enduro/X) identifier. If converting to string, then *bin* is pointer to binary identifier, casted to char pointer. It is assumed that *str* is at least **TPCONVMAXSTR** bytes long (currently 512). If converting to binary representation, then destination size must match the target structure, i.e. **CLIENTID**, **TPTRANID** or **XID** from **xa.h**.

Valid flags

TPCONVCLTID Convert **CLIENTID** type from **atmi.h** to/from string.

TPCONVTRANID Convert **TPTRANID** type from **atmi.h** to/from string. Note that string version converted is platform specific. And not will not be valid (restorable) on different platform type (i.e. little-endian, big-endian, 32bit or 64bit).

TPCONVXID Convert **XID** type from **xa.h** to/from string.

TPTOSTRING In this mode the value from *bin* parameter is converted to *str* parameter. If flag is not present then value from *str* is converted to *bin*.

If multiple TPCONV flags are present, then execution will pick up the first flag for processing in following order: **TPCONVCLTID**, **TPCONVTRANID**, **TPCONVXID**.

Chapter 3

RETURN VALUE

On success, **tpconvert()** return zero; on error, -1 is returned, with **tperrno** set to indicate the error.

Chapter 4

ERRORS

Note that **tpsterror()** returns generic error message plus custom message with debug info from last function call.

TPEINVAL *str* or *bin* params are NULL. Error is returned also in cases if *TPTOSTRING* is present, but *str* parameter is zero length (first byte 0x00). Also in cases if none of **TPCONVCLTID**, **TPCONVTRANID** or **TPCONVXID** are present this error will be returned too.

TPEINVAL Enduro/X tpinit failed - environment variables not configured, see *ex_env(5)* page.

TPESYSTEM During Enduro/X init - system failure occurred during serving. See logs i.e. user log, or debugs for more info.

TPEOS During Enduro/X init operating system failure occurred during serving. See logs i.e. user log, or debugs for more info.

Chapter 5

EXAMPLE

See `atmitest/test021_xafull/atmiclt21-tpconvert.c` for sample code.

Chapter 6

BUGS

Report bugs to support@mavimax.com

Chapter 7

SEE ALSO

`tpinit(3)` `tpsuspend(3)` `tpresume(3)` `tpservice(3)`

Chapter 8

COPYING

© Mavimax, Ltd