

# **TPRECV(3)**

**REVISION HISTORY**

NUMBER	DATE	DESCRIPTION	NAME

# Contents

<b>1 SYNOPSIS</b>	<b>1</b>
<b>2 DESCRIPTION</b>	<b>2</b>
<b>3 RETURN VALUE</b>	<b>3</b>
<b>4 ERRORS</b>	<b>4</b>
<b>5 EXAMPLE</b>	<b>5</b>
<b>6 BUGS</b>	<b>6</b>
<b>7 SEE ALSO</b>	<b>7</b>
<b>8 COPYING</b>	<b>8</b>

# Chapter 1

## SYNOPSIS

```
#include <atmi.h>
int trecv(int cd, char **data, long *len, long flags, long *revent);
For XATMI client link with -latmclt -latmi -lubf -lnstd -lpthread -lrt -lm
For XATMI server link with -latmisrv|-latmisrvnomain|-latmisrvinteg -latmi -lubf -lnstd -lpthread -lrt -lm
```

## Chapter 2

# DESCRIPTION

Receive message from open conversation, which is opened by **tpconnect()**. The incoming buffer *data* must be allocated with **tpalloc()**. If conversation receives disconnect (**TPEV\_DISCONIMM**), service error (**TPEV\_SVCERR**) or service failure (**TPEV\_SVCFAIL**), then global transaction if one in progress is aborted.

### Valid flags

**TPSIGRSTRT** Restart the system call in progress if interrupted by signal handler. This affects only underlying mq\_\* function calls.

**TPNOTIME** Ignore timeout setting (**NDRX\_TOUT** env variable). Wait for reply for infinitely.

**TPNOBLOCK** Do not block on empty queue, if not messages present, the function returns immediately.

## Chapter 3

# RETURN VALUE

On success, **tpcall()** return zero; on error, -1 is returned, with **tperrno** set to indicate the error. In case of event received, the error code is set to **TPEEVENT**.

#### *revent* return values

**TPEV\_DISCONIMM** Disconnect received from other conversation end, by issuing **tpdiscon()**. The global transaction in progress is aborted in this case.

**TPEV\_SENDONLY** The sender program issued **tpsend()** with flag **TPEV\_SENDONLY**, meaning that we become senders.

**TPEV\_SVCERR** Server died and queue was removed.

**TPEV\_SVCFAIL** Server returned **TPFAIL** with **tpreturn()**

**TPEV\_SVCSUCC** Server did **tpreturn()** with **TPSUCCESS**, connection is closed automatically after this event.

## Chapter 4

# ERRORS

Note that **tpstrerror()** returns generic error message plus custom message with debug info from last function call.

**TPEINVAL** Invalid call descriptor *cd* passed in.

**TPETIME** Service did not reply in given time (*NDRX\_TOUT*).

**TPEEVENT** Event received and it is installed into *revent* field.

**TPEPROTO** System level service failure. Server died during the message presence in service queue.

**TPESYSTEM** System failure occurred during serving. See logs i.e. user log, or debugs for more info.

**TPEOS** System failure occurred during serving. See logs i.e. user log, or debugs for more info.

---

## Chapter 5

### EXAMPLE

See **atmitest/test003\_basicconvers/atmisv3.c** for sample code.

## Chapter 6

# BUGS

Report bugs to [support@mavimax.com](mailto:support@mavimax.com)

---

## Chapter 7

### SEE ALSO

**tpconnect(3) tpsend(3) tpdiscon(3)**

## **Chapter 8**

# **COPYING**

© Mavimax, Ltd

---