

**CPMSRV(8)**

| REVISION HISTORY |      |             |      |
|------------------|------|-------------|------|
| NUMBER           | DATE | DESCRIPTION | NAME |
|                  |      |             |      |

# Contents

|   |             |   |
|---|-------------|---|
| 1 | SYNOPSIS    | 1 |
| 2 | DESCRIPTION | 2 |
| 3 | OPTIONS     | 3 |
| 4 | EXIT STATUS | 4 |
| 5 | BUGS        | 5 |
| 6 | SEE ALSO    | 6 |
| 7 | AUTHOR      | 7 |
| 8 | COPYING     | 8 |

## Chapter 1

# SYNOPSIS

**cpmrv** [*OPTIONS*]

## Chapter 2

# DESCRIPTION

Client process monitor is Enduro/X server process which is responsible for managing client processes, which are described in *ndrxconfig.xml*, *<clients>* section. The process reloads configuration file every time when timestamp is changed. If process is removed from *<clients>* section and process is stopped, then it is removed from listings. If process is running, it is left in current process model.

*cpmsrv* is servicing backend functionality for xadmin's *pc* (print clients), *bc* (boot client), *sc* (stop client) commands. Invoked via ATMI subsystem resources.

During the startup phase, all *autostart* processes are started. During the shutdown phase all started processes are shut-down, by doing standard kill signalings.

## Chapter 3

# OPTIONS

### **-i** *CHK\_INTERVAL*

*CHK\_INTERVAL* process checking interval in seconds. Default 15.

### **-k** *KILL\_INTERVAL*

*KILL\_INTERVAL* process kill interval (wait seconds between -2, -15, -9 signals). Default 30.

---

## Chapter 4

# EXIT STATUS

**0**

Success

**1**

Failure

## Chapter 5

# BUGS

Report bugs to [madars.vitolins@gmail.com](mailto:madars.vitolins@gmail.com)



## Chapter 6

## SEE ALSO

`ndrxconfig.xml`(5)

## Chapter 7

# AUTHOR

Enduro/X is created by Madars Vitolins.

## Chapter 8

# COPYING

© Mavimax, Ltd