

# TPGETNODEID(3)

| REVISION HISTORY |      |             |      |
|------------------|------|-------------|------|
| NUMBER           | DATE | DESCRIPTION | NAME |
|                  |      |             |      |

# Contents

|                   |                              |                   |
|-------------------|------------------------------|-------------------|
| <a href="#">1</a> | <a href="#">SYNOPSIS</a>     | <a href="#">1</a> |
| <a href="#">2</a> | <a href="#">DESCRIPTION</a>  | <a href="#">2</a> |
| <a href="#">3</a> | <a href="#">RETURN VALUE</a> | <a href="#">3</a> |
| <a href="#">4</a> | <a href="#">ERRORS</a>       | <a href="#">4</a> |
| <a href="#">5</a> | <a href="#">BUGS</a>         | <a href="#">5</a> |
| <a href="#">6</a> | <a href="#">SEE ALSO</a>     | <a href="#">6</a> |
| <a href="#">7</a> | <a href="#">COPYING</a>      | <a href="#">7</a> |

## Chapter 1

# SYNOPSIS

```
#include <atmi.h>
```

```
long tpgetnodeid(void);
```

For XATMI client link with *-latmiclt -latmi -lubf -lnstd -lpthread -lrt -lm*

For XATMI server link with *-latmisrvl -latmisrvnomainl -latmisrvinteg -latmi -lubf -lnstd -lpthread -lrt -lm*

## Chapter 2

# DESCRIPTION

Function returns current cluster node id. Basically that is configured in **NDRX\_NODEID** environment variable, see **ex\_env(5)** page.

## Chapter 3

# RETURN VALUE

On success, **tpgetnodeid()** return cluster node id (>0); on error, -1 is returned, with **tperrno** set to indicate the error.

## Chapter 4

# ERRORS

Note that **tpstrerror()** returns generic error message plus custom message with debug info from last function call.

**TPESYSTEM** System failure occurred during serving. See logs i.e. user log, or debugs for more info.

**TPEOS** System failure occurred during serving. See logs i.e. user log, or debugs for more info.

---

## Chapter 5

# BUGS

Report bugs to [support@mavimax.com](mailto:support@mavimax.com)



## Chapter 6

## SEE ALSO

**ex\_env(5)**

## Chapter 7

# COPYING

© Mavimax, Ltd