

**LIBNDRXXAORAS(8)**

| REVISION HISTORY |      |             |      |
|------------------|------|-------------|------|
| NUMBER           | DATE | DESCRIPTION | NAME |
|                  |      |             |      |

# Contents

|          |                              |          |
|----------|------------------------------|----------|
| <b>1</b> | <b>SYNOPSIS</b>              | <b>1</b> |
| <b>2</b> | <b>DESCRIPTION</b>           | <b>2</b> |
| <b>3</b> | <b>CONFIGURATION EXAMPLE</b> | <b>3</b> |
| <b>4</b> | <b>BUGS</b>                  | <b>4</b> |
| <b>5</b> | <b>SEE ALSO</b>              | <b>5</b> |
| <b>6</b> | <b>COPYING</b>               | <b>6</b> |

## Chapter 1

# SYNOPSIS

libndrxxaoras.so libndrxxaorad.so

```
NDRX_XA_RES_ID=1
NDRX_XA_OPEN_STR=<OPEN_STRING>
NDRX_XA_CLOSE_STR=<CLOSE_STRING>
NDRX_XA_DRIVERLIB=libndrxxaoras.so
NDRX_XA_RMLIB=libclntsh.so
NDRX_XA_LAZY_INIT=1
```

## Chapter 2

# DESCRIPTION

This is Oracle DB Switch loader for Enduro/X. Note that Enduro/X operates in multi-threaded mode, thus corresponding configuration is required, i.e. "+Threads=true" threads flags open/close strings.

## Chapter 3

# CONFIGURATION EXAMPLE

```
export NDRX_XA_RES_ID=1
export NDRX_XA_OPEN_STR="ORACLE_XA+SqlNet=$EX_ORA_SID+ACC=P/$EX_ORA_USER/$EX_ORA_PASS+SesTM ↵
    =180+LogDir=./+nolocal=f+Threads=true"
export NDRX_XA_CLOSE_STR=$NDRX_XA_OPEN_STR
export NDRX_XA_DRIVERLIB=libndrxxaoras.so
export NDRX_XA_RMLIB=libclntsh.so
export NDRX_XA_LAZY_INIT=1
```

## Chapter 4

# BUGS

Report bugs to [support@mavimax.com](mailto:support@mavimax.com)

## Chapter 5

## SEE ALSO

**libndrxxapq(8) libndrxxawsmqs(8) ndrconfig.xml(5) tmsrv(8)**

## **Chapter 6**

# **COPYING**

© Mavimax, Ltd