

TX_SET_TRANSACTION_TIMEOUT(3)

REVISION HISTORY

| NUMBER | DATE | DESCRIPTION | NAME |
|--------|------|-------------|------|
| | | | |

Contents

| | |
|-----------------------|----------|
| 1 SYNOPSIS | 1 |
| 2 DESCRIPTION | 2 |
| 3 RETURN VALUE | 3 |
| 4 ERRORS | 4 |
| 5 EXAMPLE | 5 |
| 6 BUGS | 6 |
| 7 SEE ALSO | 7 |
| 8 COPYING | 8 |

Chapter 1

SYNOPSIS

```
#include <tx.h>
int tx_set_transaction_timeout(TRANSACTION_TIMEOUT timeout);
For XATMI client link with -latmicl -latmi -lubf -lnstd -lpthread -lrt -lm
For XATMI server link with -latmisrv|-latmisrvnomain|-latmisrvinteg -latmi -lubf -lnstd -lpthread -lrt -lm
```

Chapter 2

DESCRIPTION

Function set timeout value for new transactions. The value is used when next **tx_begin(3)** is issued. The value does not affect any global transaction in progress. If value of *timeout* is set to **0** then maximum timeout value is used for transaction. Units for *timeout* is seconds.

Chapter 3

RETURN VALUE

On success, **tx_set_transaction_timeout()** return **TX_OK**; on error, error code is returned

Chapter 4

ERRORS

TX_EINVAL Invalid value of *timeout* parameter, less than 0.

TX_PROTOCOL_ERROR Transaction manager is not open by **tx_open(3)**

Chapter 5

EXAMPLE

See **atmitest/test021_xafull/atmictl21tx.c** for sample code.

Chapter 6

BUGS

Report bugs to support@mavimax.com

Chapter 7

SEE ALSO

[tx_open\(3\)](#) [tx_close\(3\)](#) [tx_begin\(3\)](#) [tx_commit\(3\)](#) [tx_rollback\(3\)](#) [tx_info\(3\)](#) [tx_set_transaction_control\(3\)](#) [tx_set_commit_return\(3\)](#)

Chapter 8

COPYING

© Mavimax, Ltd