

**BFLDDBDROP(3)**

| REVISION HISTORY |      |             |      |
|------------------|------|-------------|------|
| NUMBER           | DATE | DESCRIPTION | NAME |
|                  |      |             |      |

# Contents

|          |                     |          |
|----------|---------------------|----------|
| <b>1</b> | <b>SYNOPSIS</b>     | <b>1</b> |
| <b>2</b> | <b>DESCRIPTION</b>  | <b>2</b> |
| <b>3</b> | <b>RETURN VALUE</b> | <b>3</b> |
| <b>4</b> | <b>ERRORS</b>       | <b>4</b> |
| <b>5</b> | <b>EXAMPLE</b>      | <b>5</b> |
| <b>6</b> | <b>BUGS</b>         | <b>6</b> |
| <b>7</b> | <b>SEE ALSO</b>     | <b>7</b> |
| <b>8</b> | <b>COPYING</b>      | <b>8</b> |

## Chapter 1

# SYNOPSIS

```
#include <ubf.h>
```

```
int Bflddbdrop(EDB_txn *txn);
```

Link with *-lubf -lnstd -lm -lpthread*

## Chapter 2

# DESCRIPTION

Drop the LMDB UFB custom field databases. Note that if parameters in configuration are changed (like map size or max readers), after this call these parameters are not re-applied. The drop is done as part of the LMDB transaction, passed in the *txn* variable. The transaction is open by `edb_txn_begin()` and finished by `edb_txn_commit()` or `edb_txn_abort()`.

---

## Chapter 3

# RETURN VALUE

On success, **Bfddbunlink()** return zero; on error, -1 is returned, with **Berror** set to indicate the error.

## Chapter 4

# ERRORS

In case of error **Berror** will be non **0**. Note that **Bsterror()** returns generic error message plus custom message with debug info from last function call.

**BEINVAL** database is not loaded.

**BNOSPACE** LMDB error - no space, see logs.

**BEUNIX** LMDB error, see logs.

---

## Chapter 5

# EXAMPLE

See `atmitest/test050_ubfdb/atmict50.c` for sample code.

## Chapter 6

# BUGS

Report bugs to [support@mavimax.com](mailto:support@mavimax.com)

# Chapter 7

# SEE ALSO

**Bfddbaid(3) Bfddbname(3) Bfddbload(3) Bfddbunload(3) Bfddbunlink(3) Bfddbdel(3) Bfddbadd(3) Bfddbget(3)**

## **Chapter 8**

# **COPYING**

© Mavimax, Ltd